

# Spamhaus DNS RPZ DROP Setup

1. DNS RPZ DROP Zone Description and Master Information
2. Configuring BIND for DNS RPZ and Spamhaus DROP Zone
  - 2.1 Install/Upgrade BIND
  - 2.2 Enabling Logging of RPZ rewrites
  - 2.3 Creating a Local RPZ
  - 2.4 Defining Master and Slave Zones
  - 2.5 Enabling IXFR zone transfers
  - 2.6 Enabling DNS RPZ
  - 2.7 Testing

## 1. DNS RPZ DROP Zone Description and Master Information

The Don't Route Or Peer (DROP) zone contains netblocks that are "hijacked" or leased by professional spam or cyber-crime operations (used for dissemination of malware, ransomware, botnet controllers, and other malicious content).

In order to consume Spamhaus' RPZ you will need to setup your local recursive resolver to act as a secondary for the DROP zone with our masters which are the following:

IPv4: 34.194.195.25  
IPv4: 35.156.219.71

Note that these servers are setup to distribute via IXFR.

## 2. Configuring BIND for DNS RPZ and Spamhaus DROP

### 2.1 Install/Upgrade the most recent version of BIND

It is recommended that before you begin to implement DNS RPZ in your BIND install you upgrade to the most recent version of BIND. It is suggested that the upgrade is acquired directly from ISC (<https://www.isc.org/downloads/>) instead of updating from a software repository as some repositories will have out of date versions. This will ensure that you have the best possible support for RPZ.

### 2.2 Enabling Logging of RPZ rewrites

To monitor evaluate, and troubleshoot DNS RPZ, logging needs to be enabled in your configuration (etc/named.conf).

```
logging {  
    channel rpzlog {  
        file "rpz.log" versions unlimited size 1000m;  
        print-time yes;  
        print-category yes;  
        print-severity yes;  
        severity info;  
    };  
    category rpz { rpzlog; };  
};
```

### Quick Tip

Before you get started create a backup of your BIND configuration (named.conf) so you will have an original reference in case there is an issue with your configuration after enabling DNS RPZ

# Spamhaus DNS RPZ DROP Setup

With these settings your log file output for a DROP rewrites should look like the following:

```
1-Jan-2010 00:00:00.000 rpz: info: client @0x8ac7921a21d0 172.0.172.2#1286
(baddomain.invalid.com): rpz IP NXDOMAIN rewrite baddomain.invalid.com via
2.152.24.172.rpz-ip.drop.spamhaus.org
```

Note that only IPs are included in the DROP zone but the hostname will be displayed in the log if the user/machine attempted to access a hostname.

## Quick Tip

Consider exporting your logs into a database or log analysis software to have a better visualization of the data produced in the DNS RPZ logs.

## 2.3 Creating a Local RPZ

A local RPZ is needed for creating exceptions (passthru) to feeds that you have subscribed to and also create additional blocking or whitelisted actions. This zone is created in `/var/named`:

```
$TTL 300
@      IN SOA  localhost.local.rpz. (
                20170913      ; Serial number
                60            ; Refresh every minute
                60            ; Retry every minute
                432000        ; Expire in 5 days
                60 )          ; negative caching ttl 1 minute
      IN NS  LOCALHOST.
detecue.com      IN CNAME  rpz-passthru.
*.detecue.com   IN CNAME  rpz-passthru.
32.25.195.34.rpz-ip  IN CNAME  rpz-passthru.      ;whitelist 34.194.195.25/32
32.71.219.35.rpz-ip  IN CNAME  rpz-passthru.      ;whitelist 35.156.219.71/32
invalid.com     IN CNAME  .                ;local block against invalid.com
*.invalid.com  IN CNAME  .                ;local block against *.invalid.com
```

You can name your local zone whatever you wish. Anything after IN SOA localhost. is what your local zone will be named. Remember to include a . at the end of the name. The following 4 record details after Serial Number (Refresh, Retry, Expire, Negative result TTL) are displayed in seconds and are always listed in this order.

It is recommended that anything that is critical to your network be added into this zone as a rpz-passthru. Any internal domains and network IPs should be included in this zone.

# Spamhaus DNS RPZ DROP Setup

## 2.4 Defining Master and Slave Zones

BIND requests that you define which zones that will be used to action on DNS queries to your resolver in your named.conf file. First the local master zone should be defined.

```
zone "local.rpz" {
    type master;
    file "local.rpz";
    allow-transfer { none; };
    allow-query { localhost; };
};
```

### Quick Tip

When putting DNS RPZ on your resolver ensure that you have a low TTL. This will avoid having a malicious or compromised site still resolve when it is included in an DNS RPZ feed.

The reason that allow-query is set to localhost is so only the resolver will be able to access the zones defined.

Next your slave zones that will pull from Spamhaus' masters will need to be defined and will look like the following:

```
zone "drop.rpz.spamhaus.org" {
    type slave;
    file "dbl.rpz.spamhaus.org";
    masters { 34.194.195.25; 35.156.219.17; };
    allow-transfer { none; };
    allow-query { localhost; };
};
```

Since the slave zones are not located locally on the resolver the master zones must be defined in every slave zone. Also the slave zones will be set to localhost.

## 2.5 Enabling IXFR zone transfers

Since DNS RPZ is designed to provide updates to malicious threats as quickly as possible it is required that incremental (IXFR) transfers be enabled when accessing our DNS RPZ feeds. This will ensure that only the most up to date information is provided. This setting is enabled in your named.conf file:

```
options {
    ixfr-from-difference yes;
};
```

# Spamhaus DNS RPZ DROP Setup

## 2.6 Enabling DNS RPZ

The last step is adding response policy to your named.conf file:

```
options {
    response-policy {
        zone "local.rpz";
        zone "drop.rpz.spamhaus.org POLICY RPZ-PASSTHRU";
    };
};
```

In this configuration POLICY RPZ-PASSTHRU is included in enabling DNS RPZ. With passthru no enforcement will take place but the action of the passthru will be logged. In order to enforce the entire in a given zone POLICY RPZ-PASSTHRU should be removed.

## 2.7 Testing

Now that DNS RPZ is enabled in your BIND configuration, testing that everything is setup correctly should be done. There are a few ways to test if DNS RPZ is working as intended, by command line, browser, or checking logging.

To test via command line running an nslookup or dig command will return NXDomain or does not exist depending on what OS you are using to test.

Testing in a browser will return "This site cannot be reached", "This webpage is not available" or similar.

With logging you will need to check your rpz.log file located in /var/named. Note that you will only get a result if you attempted to access something that is contained in one of your zones.

When testing in a browser or via command line, if there is resolution of the domain or IP address there is a misconfiguration in your DNS RPZ. (Remember to remove POLICY RPZ-PASSTHRU when testing if resolution is being blocked)

### Quick Tip

Run any new DNS RPZ feed in POLICY RPZ-PASSTHRU for 10 to 14 days. This will allow logs to still be generated for the rewrites that would have happened if the feed was enforcing. With this information you will know if there are any impacted sites on the feed.